

# GT.M

## Release Notes

V6.3-010

Empowering  
the Financial World

FIS

## Contact Information

GT.M Group  
Fidelity National Information Services, Inc.  
200 Campus Drive  
Collegeville, PA 19426  
United States of America

GT.M Support for customers: [gtmsupport@fisglobal.com](mailto:gtmsupport@fisglobal.com)  
Automated attendant for 24 hour support: +1 (484) 302-3248  
Switchboard: +1 (484) 302-3160  
Website: <http://fis-gtm.com>

## Legal Notice

Copyright ©2019 Fidelity National Information Services, Inc. and/or its subsidiaries. All Rights Reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts and no Back-Cover Texts.

GT.M™ is a trademark of Fidelity National Information Services, Inc. Other trademarks are the property of their respective owners.

This document contains a description of GT.M and the operating instructions pertaining to the various functions that comprise the system. This document does not contain any commitment of FIS. FIS believes the information in this publication is accurate as of its publication date; such information is subject to change without notice. FIS is not responsible for any errors or defects.

### Revision History

Revision History		
Revision 1.0	31 October 2019	V6.3-010

# Table of Contents

V6.3-010 .....	1
Overview .....	1
Conventions .....	1
Platforms .....	2
Platform support lifecycle .....	4
32- vs. 64-bit platforms .....	4
Call-ins and External Calls .....	4
Internationalization (Collation) .....	5
Environment Translation .....	5
Additional Installation Instructions .....	5
.....	6
Upgrading to GT.M V6.3-010 .....	7
Stage 1: Global Directory Upgrade .....	7
Stage 2: Database Files Upgrade .....	8
Stage 3: Replication Instance File Upgrade .....	10
Stage 4: Journal Files Upgrade .....	10
Stage 5: Trigger Definitions Upgrade .....	11
Downgrading to V5 or V4 .....	11
Managing M mode and UTF-8 mode .....	12
Setting the environment variable TERM .....	13
Installing Compression Libraries .....	13
Change History .....	15
V6.3-010 .....	15
Language .....	17
System Administration .....	18
Other .....	20
Error and Other Messages .....	21
DSEINVALBLKID  .....	21
FNTRANSERROR  .....	21
PARBUFSM  .....	21
VERMISMATCH  .....	21
ZATRANSCOL  .....	21

# V6.3-010

## Overview

V6.3-010 provides new options from \$ZATRANSFORM(), the option to specify more precise keys to MUPIP SIZE, the ability to extract from journal files without needing their associated database files, additional classification information in MUPIP INTEG reports, and more uniform behavior from ZLINK. V6.3-010 also includes other fixes and enhancements. For more information, refer to the Change History section.

Items marked with 🟢 document new or different capabilities.

Please pay special attention to the items marked with the symbols 🟡 as those document items that have a possible impact on existing code, practice or process.



### Note

Messages are not part of the GT.M API whose stability we strive to maintain. Make sure that you review any automated scripting that parses GT.M messages.

## Conventions

This document uses the following conventions:

<b>Flag/Qualifiers</b>	-
<b>Program Names or Functions</b>	upper case. For example, MUPIP BACKUP
<b>Examples</b>	lower case. For example: mupip backup -database ACN,HIST /backup
<b>Reference Number</b>	A reference number is used to track software enhancements and support requests. It is enclosed between parentheses ().
<b>Platform Identifier</b>	Where an item affects only specific platforms, the platforms are listed in square brackets, e.g., [AIX]



### Note

The term UNIX refers to the general sense of all platforms on which GT.M uses a POSIX API. As of this date, this includes: AIX and GNU/Linux on x86 (32- and 64-bits).

The following table summarizes the new and revised replication terminology and qualifiers.

Pre V5.5-000 terminology	Pre V5.5-000 qualifier	Current terminology	Current qualifiers
originating instance or primary instance	-rootprimary	originating instance or originating primary instance.	-updok (recommended) -rootprimary (still accepted)

Pre V5.5-000 terminology	Pre V5.5-000 qualifier	Current terminology	Current qualifiers
		Within the context of a replication connection between two instances, an originating instance is referred to as source instance or source side. For example, in an B<-A->C replication configuration, A is the source instance for B and C.	
replicating instance (or secondary instance) and propagating instance	N/A for replicating instance or secondary instance.  -propagateprimary for propagating instance	replicating instance.  Within the context of a replication connection between two instances, a replicating instance that receives updates from a source instance is referred to as receiving instance or receiver side. For example, in an B<-A->C replication configuration, both B and C can be referred to as a receiving instance.	-updnok
N/A	N/A	supplementary instance.  For example, in an A->P->Q replication configuration, P is the supplementary instance. Both A and P are originating instances.	-updok

Effective V6.0-000, GT.M documentation adopted IEC standard Prefixes for binary multiples. This document therefore uses prefixes Ki, Mi and Ti (e.g., 1MiB for 1,048,576 bytes). Over time, we'll update all GT.M documentation to this standard.

- ✔ denotes a new feature that requires updating the manuals.
- ⚠ denotes a new feature or an enhancement that may not be upward compatible and may affect an existing application.
- ✖ denotes deprecated messages.
- ⚠ denotes revised messages.
- ➕ denotes added messages.

## Platforms

Over time, computing platforms evolve. Vendors obsolete hardware architectures. New versions of operating systems replace old ones. We at FIS continually evaluate platforms and versions of platforms that should be Supported for GT.M. In the table below, we document not only the ones that are currently Supported for this release, but also alert you to our future plans given the evolution of computing platforms. If you are an FIS customer, and these plans would cause you hardship, please contact your FIS account executive promptly to discuss your needs.

Each GT.M release is extensively tested by FIS on a set of specific versions of operating systems on specific hardware architectures (the combination of operating system and hardware architecture is referred to as a platform). This set of specific versions is considered Supported. There may be other versions of the same operating systems on which a GT.M release may not have been tested, but on which the FIS GT.M Group knows of no reason why GT.M would not work. This larger set of versions is considered Supportable. There is an even larger set of platforms on which GT.M may well run satisfactorily, but where the FIS GT.M team lacks the knowledge to determine whether GT.M is Supportable. These are considered Unsupported. Contact FIS GT.M Support with inquiries about your preferred platform.

V6.3-010

As of the publication date, FIS supports this release on the hardware and operating system versions below. Contact FIS for a current list of Supported platforms. The reference implementation of the encryption plugin has its own additional requirements, should you opt to use it as included with GT.M.

Platform	Supported Versions	Notes
IBM Power Systems AIX	7.1 TL 4, 7.2	<p>Only 64-bit versions of AIX with POWER7 as the minimum required CPU architecture level are Supported.</p> <p>While GT.M supports both UTF-8 mode and M mode on this platform, there are problems with the AIX ICU utilities that prevent FIS from testing 4-byte UTF-8 characters as comprehensively on this platform as we do on others.</p> <p>Running GT.M on AIX 7.1 requires APAR IZ87564, a fix for the POW() function, to be applied. To verify that this fix has been installed, execute <b>instfix -ik IZ87564</b>.</p> <p>AIX 7.1 TL 5 is Supportable.</p> <p>Only the AIX jfs2 filesystem is Supported. Other filesystems, such as jfs1 are Supportable, but not Supported. FIS strongly recommends use of the jfs2 filesystem on AIX; use jfs1 only for existing databases not yet migrated to a jfs2 filesystem.</p>
x86_64 GNU/Linux	Red Hat Enterprise Linux 7.6; Ubuntu 16.04 LTS	<p>To run 64-bit GT.M processes requires both a 64-bit kernel as well as 64-bit hardware.</p> <p>GT.M should also run on recent releases of other major Linux distributions with a contemporary Linux kernel (2.6.32 or later), glibc (version 2.12 or later) and ncurses (version 5.7 or later).</p> <p>Due to build optimization and library incompatibilities, GT.M versions older than V6.2-000 are incompatible with glibc 2.24 and up. This incompatibility has not been reported by a customer, but was observed on internal test systems that use the latest Linux software distributions from Fedora (26), Debian (unstable), and Ubuntu (17.10). In internal testing, processes either hung or encountered a segmentation violation (SIG-11) during operation. Customers upgrading to Linux distributions that utilize glibc 2.24+ must upgrade their GT.M version at the same time as or before the OS upgrade.</p> <p>GT.M requires the libtinfo library. If it is not already installed on your system, and is available using the package manager, install it using the package manager. If a libtinfo package is not available:</p> <ul style="list-style-type: none"> <li>* Find the directory where libncurses.so is installed on your system.</li> <li>* Change to that directory and make a symbolic link to libncurses.so.&lt;ver&gt; from libtinfo.so.&lt;ver&gt;. Note that some of the libncurses.so entries may themselves be symbolic links, for example, libncurses.so.5 may itself be a symbolic link to libncurses.so.5.9.</li> </ul> <p>To support the optional WRITE /TLS fifth argument (the ability to provide / override options in the tlsid section of the encryption configuration file), the reference implementation of the encryption plugin requires libconfig 1.4.x.</p>

Platform	Supported Versions	Notes
		<p>Although GT.M itself does not require libelf, the geteuid program used by the GT.M installation script requires libelf (packaged as libelf1 on current Debian/Ubuntu distributions and elfutils-libelf on RHEL 6 &amp; 7).</p> <p>Only the ext4 and xfs filesystems are Supported. Other filesystems are Supportable, but not Supported. Furthermore, if you use the NODEFER_ALLOCATE feature, FIS strongly recommends that you use xfs. If you must use NODEFER_ALLOCATE with ext4, you <i>must</i> ensure that your kernel includes commit d2dc317d564a46dfc683978a2e5a4f91434e9711 (search for d2dc317d564a46dfc683978a2e5a4f91434e9711 at <a href="https://www.kernel.org/pub/linux/kernel/v4.x/ChangeLog-4.0.3">https://www.kernel.org/pub/linux/kernel/v4.x/ChangeLog-4.0.3</a>). The Red Hat Bugzilla identifier for the bug is 1213487. With NODEFER_ALLOCATE, do not use any filesystem other than ext4 and a kernel with the fix, or xfs.</p>
x86 GNU/Linux	Debian 9 (Stretch)	<p>This 32-bit version of GT.M runs on either 32- or 64-bit x86 platforms; we expect the x86_64 GNU/Linux version of GT.M to be preferable on 64-bit hardware. Running a 32-bit GT.M on a 64-bit GNU/Linux requires 32-bit libraries to be installed. The CPU must have an instruction set equivalent to 586 (Pentium) or better.</p> <p>Please also refer to the notes above on x86_64 GNU/Linux.</p>

## Platform support lifecycle

FIS usually supports new operating system versions six months or so after stable releases are available and we usually support each version for a two year window. GT.M releases are also normally supported for two years after release. While FIS will attempt to provide support to customers in good standing for any GT.M release and operating system version, our ability to provide support diminishes after the two year window.

GT.M cannot be patched, and bugs are only fixed in new releases of software.

## 32- vs. 64-bit platforms

The same application code runs on both 32-bit and 64-bit platforms; however there are operational differences between them (for example, auto-relink and the ability to use GT.M object code from shared libraries exist only on 64-bit platforms). Please note that:

- \* You must compile the application code separately for each platform. Even though the M source code is the same, the generated object modules are different - the object code differs between x86 and x86\_64.
- \* Parameter-types that interface GT.M with non-M code using C calling conventions must match the data-types on their target platforms. Mostly, these parameters are for call-ins, external calls, internationalization (collation) and environment translation, and are listed in the tables below. Note that most addresses on 64-bit platforms are 8 bytes long and require 8 byte alignment in structures whereas all addresses on 32-bit platforms are 4 bytes long and require 4-byte alignment in structures.

## Call-ins and External Calls

Parameter type	32-Bit	64-bit	Remarks
gtm_long_t	4-byte (32-bit)	8-byte (64-bit)	gtm_long_t is much the same as the C language long type.

Parameter type	32-Bit	64-bit	Remarks
gtm_ulong_t	4-byte	8-byte	gtm_ulong_t is much the same as the C language unsigned long type.
gtm_int_t	4-byte	4-byte	gtm_int_t has 32-bit length on all platforms.
gtm_uint_t	4-byte	4-byte	gtm_uint_t has 32-bit length on all platforms



### Caution

If your interface uses gtm\_long\_t or gtm\_ulong\_t types but your interface code uses int or signed int types, failure to revise the types so they match on a 64-bit platform will cause the code to fail in unpleasant, potentially dangerous, and hard to diagnose ways.

## Internationalization (Collation)

Parameter type	32-Bit	64-bit	Remarks
gtm_descriptor in gtm_descript.h	4-byte	8-byte	Although it is only the address within these types that changes, the structures may grow by up to 8 bytes as a result of compiler padding to meet platform alignment requirements.



### Important

Assuming other aspects of code are 64-bit capable, collation routines should require only recompilation.

## Environment Translation

Parameter type	32-Bit	64-bit	Remarks
gtm_string_t type in gtmxc_types.h	4-byte	8-byte	Although it is only the address within these types that changes, the structures may grow by up to 8 bytes as a result of compiler padding to meet platform alignment requirements.



### Important

Assuming other aspects of code are 64-bit capable, environment translation routines should require only recompilation.

## Additional Installation Instructions

To install GT.M, see the "Installing GT.M" section in the GT.M Administration and Operations Guide. For minimal down time, upgrade a current replicating instance and restart replication. Once that replicating instance is current, switch it to become the originating instance. Upgrade the prior originating instance to become a replicating instance, and perform a switchover when you want it to resume an originating primary role.



### Caution

Never replace the binary image on disk of any executable file while it is in use by an active process. It may lead to unpredictable results. Depending on the operating system, these results include but are not limited to denial of service (that is, system lockup) and damage to files that these processes have open (that is, database structural damage).

- \* FIS strongly recommends installing each version of GT.M in a separate (new) directory, rather than overwriting a previously installed version. If you have a legitimate need to overwrite an existing GT.M installation with a new version, you must first shut down all processes using the old version. FIS suggests installing GT.M V6.3-010 in a Filesystem Hierarchy Standard compliant location such as /usr/lib/fis-gtm/V6.3-010\_arch (for example, /usr/lib/fis-gtm/V6.3-010\_x86 on 32-bit Linux systems). A location such as /opt/fis-gtm/V6.3-010\_arch would also be appropriate. Note that the *arch* suffix is especially important if you plan to install 32- and 64-bit versions of the same release of GT.M on the same system.
- \* Use the appropriate MUPIP command (e.g. ROLLBACK, RECOVER, RUNDOWN) of the old GT.M version to ensure all database files are cleanly closed.
- \* Make sure gtmsecshr is not running. If gtmsecshr is running, first stop all GT.M processes including the DSE, LKE and MUPIP utilities and then perform a **MUPIP STOP *pid\_of\_gtmsecshr***.
- \* Starting with V6.2-000, GT.M no longer supports the use of the deprecated \$gtm\_dbkeys and the master key file it points to for database encryption. To convert master files to the libconfig format, please click  to download the CONVDBKEYS.m program and follow instructions in the comments near the top of the program file. You can also download CONVDBKEYS.m from <http://tinco.pair.com/bhaskar/gtm/doc/articles/downloadables/CONVDBKEYS.m>. If you are using \$gtm\_dbkeys for database encryption, please convert master key files to libconfig format immediately after upgrading to V6.2-000 or later. Also, modify your environment scripts to include the use of gtmcrypt\_config environment variable.

## Recompile

- \* Recompile all M and C source files.

## Rebuild Shared Libraries or Images

- \* Rebuild all Shared Libraries after recompiling all M and C source files.
- \* If your application is not using object code shared using GT.M's auto-relink functionality, please consider using it.

## Compiling the Reference Implementation Plugin

If you plan to use database encryption, TLS replication, or TLS sockets, you must compile the reference implementation plugin to match the shared library dependencies unique to your platform. The instructions for compiling the Reference Implementation plugin are as follows:

1. Install the development headers and libraries for libgcrypt, libpgpme, libconfig, and libssl. On Linux, the package names of development libraries usually have a suffix such as -dev or -devel and are available through the package manager. For example, on Ubuntu\_x86\_64 a command like the following installs the required development libraries:

```
sudo apt-get install libgcrypt11-dev libpgpme11-dev libconfig-dev libssl-dev
```

Note that the package names may vary by distribution / version.

2. Unpack \$gtm\_dist/plugin/gtmcrypt/source.tar to a temporary directory.

```
mkdir /tmp/plugin-build
cd /tmp/plugin-build
cp $gtm_dist/plugin/gtmcrypt/source.tar .
tar -xvf source.tar
```

3. Follow the instructions in the README.

- \* Open Makefile with your editor; review and edit the common header (IFLAGS) and library paths (LIBFLAGS) in the Makefile to reflect those on your system.

- \* Define the `gtm_dist` environment variable to point to the absolute path for the directory where you have GT.M installed
- \* Copy and paste the commands from the README to compile and install the encryption plugin with the permissions defined at install time



## Caution

These are separate steps to compile the encryption plugin for GT.M versions V5.3-004 through V6.3-000 when OpenSSL 1.1 is installed and OpenSSL 1.0.x libraries are still available.

- \* Download the most recent OpenSSL 1.0.x version
- \* Compile and install (default installs to `/usr/local/ssl`)

```
./config && make install
```

- \* Adjust the configuration : Move the newly installed libraries out of the way

```
mv /usr/local/ssl/lib /usr/local/ssl/lib.donotuse
```

- \* Adjust the configuration : Create another `/usr/local/ssl/lib` and symlink the existing 1.0.x library into it as the default. This ensures that the encryption plugin is compiled using the compatible OpenSSL 1.0.x library. Adjust the path below as necessary.

```
mkdir /usr/local/ssl/lib && ln -s /path/to/existing/libssl.so.1.0.x /usr/local/ssl/libssl.so
```

- \* Recompile the encryption plugin following the above directions.
- \* Remove `/usr/local/ssl/lib.donotuse` to avoid future complications.

## Upgrading to GT.M V6.3-010

The GT.M database consists of four types of components- database files, journal files, global directories, and replication instance files. The format of some database components differs for 32-bit and 64-bit GT.M releases for the x86 GNU/Linux platform.

GT.M upgrade procedure for V6.3-010 consists of 5 stages:

- \* Stage 1: Global Directory Upgrade
- \* Stage 2: Database Files Upgrade
- \* Stage 3: Replication Instance File Upgrade
- \* Stage 4: Journal Files Upgrade
- \* Stage 5: Trigger Definitions Upgrade

Read the upgrade instructions of each stage carefully. Your upgrade procedure for GT.M V6.3-010 depends on your GT.M upgrade history and your current version.

### Stage 1: Global Directory Upgrade

FIS strongly recommends you back up your Global Directory file before upgrading. There is no one-step method for downgrading a Global Directory file to an older format.

**To upgrade from any previous version of GT.M:**

- \* Open your Global Directory with the GDE utility program of GT.M V6.3-010.
- \* Execute the EXIT command. This command automatically upgrades the Global Directory.

**To switch between 32- and 64-bit global directories on the x86 GNU/Linux platform:**

1. Open your Global Directory with the GDE utility program on the 32-bit platform.
2. On GT.M versions that support SHOW -COMMAND, execute SHOW -COMMAND -FILE=file-name. This command stores the current Global Directory settings in the specified file.
3. On GT.M versions that do not support GDE SHOW -COMMAND, execute the SHOW -ALL command. Use the information from the output to create an appropriate command file or use it as a guide to manually enter commands in GDE.
4. Open GDE on the 64-bit platform. If you have a command file from 2. or 3., execute @file-name and then run the EXIT command. These commands automatically create the Global Directory. Otherwise use the GDE output from the old Global Directory and apply the settings in the new environment.

An analogous procedure applies in the reverse direction.

If you inadvertently open a Global Directory of an old format with no intention of upgrading it, execute the QUIT command rather than the EXIT command.

If you inadvertently upgrade a global directory, perform the following steps to downgrade to an old GT.M release:

- \* Open the global directory with the GDE utility program of V6.3-010.
- \* Execute the SHOW -COMMAND -FILE=file-name command. This command stores the current Global Directory settings in the file-name command file. If the old version is significantly out of date, edit the command file to remove the commands that do not apply to the old format. Alternatively, you can use the output from SHOW -ALL or SHOW -COMMAND as a guide to manually enter equivalent GDE commands for the old version.

## Stage 2: Database Files Upgrade

Before starting the database file upgrade, use the prior GT.M version to perform an appropriate MUIP action to removes abandoned GT.M database semaphores and releases any IPC resources.

### To upgrade from GT.M V6\*:

There is no explicit procedure to upgrade a V6 database file when upgrading to a newer V6 version. After upgrading the Global Directory, opening a V6 database with a newer V6 GT.M process automatically upgrades the fields in the database file header.

### To upgrade from GT.M V5.0\*/V5.1\*/V5.2\*/V5.3\*/V5.4\*/V5.5:

A V6 database file is a superset of a V5 database file and has potentially longer keys and records. Therefore, upgrading a database file requires no explicit procedure. After upgrading the Global Directory, opening a V5 database with a V6 process automatically upgrades fields in the database fileheader.

A database created with V6 supports up to 992Mi blocks and is not backward compatible. V6 databases that take advantage of V6 limits on key size and records size cannot be downgraded. Use MUIP DOWNGRADE -VERSION=V5 to downgrade a V6 database back to V5 format provided it meets the database downgrade requirements. For more information on downgrading a database, refer to Downgrading to V5 or V4.



### Important

A V5 database that has been automatically upgraded to V6 can perform all GT.M V6.3-010 operations. However, that database can only grow to the maximum size of the version in which it was originally created. A database created

on V5.0-000 through V5.3-003 has maximum size of 128Mi blocks. A database created on V5.4-000 through V5.5-000 has a maximum size of 224Mi blocks. A database file created with V6.0-000 (or above) can grow up to a maximum of 992Mi blocks. This means that, for example, the maximum size of a V6 database file having 8KiB block size is 7936GiB (8KiB\*992Mi).



## Important

In order to perform a database downgrade you must perform a MUPIP INTEG -NOONLINE. If the duration of the MUPIP INTEG exceeds the time allotted for an upgrade you should rely on a rolling upgrade scheme using replication.

If your database has any previously used but free blocks from an earlier upgrade cycle (V4 to V5), you may need to execute the MUPIP REORG -UPGRADE command. If you have already executed the MUPIP REORG -UPGRADE command in a version prior to V5.3-003 and if subsequent versions cannot determine whether MUPIP REORG -UPGRADE performed all required actions, it sends warnings to the syslog requesting another run of MUPIP REORG -UPGRADE. In that case, perform any one of the following steps:

- \* Execute the MUPIP REORG -UPGRADE command again, or
- \* Execute the DSE CHANGE -FILEHEADER -FULLY\_UPGRADED=1 command to stop the warnings.



## Caution

Do not run the DSE CHANGE -FILEHEADER -FULLY\_UPGRADED=1 command unless you are absolutely sure of having previously run a MUPIP REORG -UPGRADE from V5.3-003 or later. An inappropriate DSE CHANGE -FILEHEADE -FULLY\_UPGRADED=1 may lead to database integrity issues.

You do not need to run MUPIP REORG -UPGRADE on:

- \* A database that was created by a V5 MUPIP CREATE
- \* A database that has been completely processed by a MUPIP REORG -UPGRADE from V5.3-003 or later.

For additional upgrade considerations, refer to Database Compatibility Notes.

### To upgrade from a GT.M version prior to V5.000:

You need to upgrade your database files only when there is a block format upgrade from V4 to V5. However, some versions, for example, database files which have been initially been created with V4 (and subsequently upgraded to a V5 format) may additionally need a MUPIP REORG -UPGRADE operation to upgrade previously used but free blocks that may have been missed by earlier upgrade tools.

- \* Upgrade your database files using in-place or traditional database upgrade procedure depending on your situation. For more information on in-place/traditional database upgrade, see Database Migration Technical Bulletin.
- \* Run the MUPIP REORG -UPGRADE command. This command upgrades all V4 blocks to V5 format.



## Note

Databases created with GT.M releases prior to V5.0-000 and upgraded to a V5 format retain the maximum size limit of 64Mi (67,108,864) blocks.

## Database Compatibility Notes

- \* Changes to the database file header may occur in any release. GT.M automatically upgrades database file headers as needed. Any changes to database file headers are upward and downward compatible within a major database release number, that is, although processes from

only one GT.M release can access a database file at any given time, processes running different GT.M releases with the same major release number can access a database file at different times.

- \* Databases created with V5.3-004 through V5.5-000 can grow to a maximum size of 224Mi (234,881,024) blocks. This means, for example, that with an 8KiB block size, the maximum database file size is 1,792GiB; this is effectively the size of a single global variable that has a region to itself and does not itself span regions; a database consists of any number of global variables. A database created with GT.M versions V5.0-000 through V5.3-003 can be upgraded with MUPIP UPGRADE to increase the limit on database file size from 128Mi to 224Mi blocks.
- \* Databases created with V5.0-000 through V5.3-003 have a maximum size of 128Mi (134, 217,728) blocks. GT.M versions V5.0-000 through V5.3-003 can access databases created with V5.3-004 and later as long as they remain within a 128Mi block limit.
- \* Database created with V6.0-000 or above have a maximum size of 1,040,187,392(992Mi) blocks.
- \* For information on downgrading a database upgraded from V6 to V5, refer to: Downgrading to V5 or V4.

## Stage 3: Replication Instance File Upgrade

V6.3-010 does not require new replication instance files if you are upgrading from V5.5-000. However, V6.3-010 requires new replication instance files if you are upgrading from any version prior to V5.5-000. Instructions for creating new replication instance files are in the Database Replication chapter of the GT.M Administration and Operations Guide. Shut down all Receiver Servers on other instances that are to receive updates from this instance, shut down this instance Source Server(s), recreate the instance file, restart the Source Server(s) and then restart any Receiver Server for this instance with the -UPDATERESYNC qualifier.



### Note

Without the -UPDATERESYNC qualifier, the replicating instance synchronizes with the originating instance using state information from both instances and potentially rolling back information on the replicating instance. The -UPDATERESYNC qualifier declares the replicating instance to be in a wholesome state matching some prior (or current) state of the originating instance; it causes MUPIP to update the information in the replication instance file of the originating instance and not modify information currently in the database on the replicating instance. After this command, the replicating instance catches up to the originating instance starting from its own current state. Use -UPDATERESYNC only when you are absolutely certain that the replicating instance database was shut down normally with no errors, or appropriately copied from another instance with no errors.



### Important

You must always follow the steps described in the Database Replication chapter of the GT.M Administration and Operations Guide when migrating from a logical dual site (LDS) configuration to an LMS configuration, even if you are not changing GT.M releases.

## Stage 4: Journal Files Upgrade

On every GT.M upgrade:

- \* Create a fresh backup of your database.
- \* Generate new journal files (without back-links).



### Important

This is necessary because MUPIP JOURNAL cannot use journal files from a release other than its own for RECOVER, ROLLBACK, or EXTRACT.

## Stage 5: Trigger Definitions Upgrade

If you are upgrading from V5.4-002A/V5.4-002B/V5.5-000 to V6.3-010 and you have database triggers defined in V6.2-000 or earlier, you need to ensure that your trigger definitions are wholesome in the older version and then run MUPIP TRIGGER -UPGRADE. If you have doubts about the wholesomeness of the trigger definitions in the old version use the instructions below to capture the definitions delete them in the old version (-\*), run MUPIP TRIGGER -UPGRADE in V6.3-010 and then reload them as described below.

You need to extract and reload your trigger definitions only if you are upgrading from V5.4-000/V5.4-000A/V5.4-001 to V6.3-010 or if you find your prior version trigger definitions have problems. For versions V5.4-000/V5.4-000A/V5.4-001 this is necessary because multi-line XECUTEs for triggers require a different internal storage format for triggers which makes triggers created in V5.4-000/V5.4-000A/V5.4-001 incompatible with V5.4-002/V5.4-002A/V5.4-002B/V5.5-000/V6.0-000/V6.0-001/V6.3-010.

To extract and reapply the trigger definitions on V6.3-010 using MUPIP TRIGGER:

1. Using the old version, execute a command like **mupip trigger -select="\*" trigger\_defs.trg**. Now, the output file trigger\_defs.trg contains all trigger definitions.
2. Place -\* at the beginning of the trigger\_defs.trg file to remove the old trigger definitions.
3. Using V6.3-010, run **mupip trigger -triggerfile=trigger\_defs.trg** to reload your trigger definitions.

To extract and reload trigger definitions on a V6.3-010 replicating instance using \$ZTRIGGER():

1. Shut down the instance using the old version of GT.M.
2. Execute a command like **mumps -run %XCMD 'i \$ztrigger("select") > trigger\_defs.trg**. Now, the output file trigger\_defs.trg contains all trigger definitions.
3. Turn off replication on all regions.
4. Run **mumps -run %XCMD 'i \$ztrigger("item","-\*")** to remove the old trigger definitions.
5. Perform the upgrade procedure applicable for V6.3-010.
6. Run **mumps -run %XCMD 'if \$ztrigger("file","trigger\_defs.trg")** to reapply your trigger definitions.
7. Turn replication on.
8. Connect to the originating instance.



### Note

Reloading triggers rennumbers automatically generated trigger names.

## Downgrading to V5 or V4

You can downgrade a GT.M V6 database to V5 or V4 format using MUPIP DOWNGRADE.

Starting with V6.0-000, MUPIP DOWNGRADE supports the -VERSION qualifier with the following format:

```
MUPIP DOWNGRADE -VERSION=[V5|V4]
```

-VERSION specifies the desired version for the database header.

**To qualify for a downgrade from V6 to V5, your database must meet the following requirements:**

1. The database was created with a major version no greater than the target version.

2. The database does not contain any records that exceed the block size (spanning nodes).
3. The sizes of all the keys in database are less than 256 bytes.
4. There are no keys present in database with size greater than the Maximum-Key-Size specification in the database header, that is, Maximum-Key-Size is assured.
5. The maximum Record size is small enough to accommodate key, overhead, and value within a block.

To verify that your database meets all of the above requirements, execute MUPIP INTEG -NOONLINE. Note that the integrity check requires the use of -NOONLINE to ensure no concurrent updates invalidate the above requirements. Once assured that your database meets all the above requirements, MUPIP DOWNGRADE -VERSION=V5 resets the database header to V5 elements which makes it compatible with V5 versions.

To qualify for a downgrade from V6 to V4, your database must meet the same downgrade requirements that are there for downgrading from V6 to V5.

If your database meets the downgrade requirements, perform the following steps to downgrade to V4:

1. In a GT.M V6.3-010 environment:
  - a. Execute MUPIP SET -VERSION=v4 so that GT.M writes updates blocks in V4 format.
  - b. Execute MUPIP REORG -DOWNGRADE to convert all blocks from V6 format to V4 format.
2. Bring down all V6 GT.M processes and execute MUPIP RUNDOWN -FILE on each database file to ensure that there are no processes accessing the database files.
3. Execute MUPIP DOWNGRADE -VERSION=V4 to change the database file header from V6 to V4.
4. Restore or recreate all the V4 global directory files.
5. Your database is now successfully downgraded to V4.

---

## Managing M mode and UTF-8 mode

With International Components for Unicode (ICU) version 3.6 or later installed, GT.M's UTF-8 mode provides support for Unicode® (ISO/IEC-10646) character strings. On a system that does not have ICU 3.6 or later installed, GT.M only supports M mode.

On a system that has ICU installed, GT.M optionally installs support for both M mode and UTF-8 mode, including a utf8 subdirectory of the directory where GT.M is installed. From the same source file, depending upon the value of the environment variable gtm\_chset, the GT.M compiler generates an object file either for M mode or UTF-8 mode. GT.M generates a new object file when it finds both a source and an object file, and the object predates the source file and was generated with the same setting of \$gtm\_chset/\$ZCHset. A GT.M process generates an error if it encounters an object file generated with a different setting of \$gtm\_chset/\$ZCHset than that processes' current value.

Always generate an M object module with a value of \$gtm\_chset/\$ZCHset matching the value processes executing that module will have. As the GT.M installation itself contains utility programs written in M, their object files also conform to this rule. In order to use utility programs in both M mode and UTF-8 mode, the GT.M installation ensures that both M and UTF-8 versions of object modules exist, the latter in the utf8 subdirectory. This technique of segregating the object modules by their compilation mode prevents both frequent recompiles and errors in installations where both modes are in use. If your installation uses both modes, consider a similar pattern for structuring application object code repositories.

GT.M is installed in a parent directory and a utf8 subdirectory as follows:

- \* Actual files for GT.M executable programs (mumps, mupip, dse, lke, and so on) are in the parent directory, that is, the location specified for installation.
- \* Object files for programs written in M (GDE, utilities) have two versions - one compiled with support for UTF-8 mode in the utf8 subdirectory, and one compiled without support for UTF-8 mode in the parent directory. Installing GT.M generates both versions of object

files, as long as ICU 3.6 or greater is installed and visible to GT.M when GT.M is installed, and you choose the option to install UTF-8 mode support. Note that on 64-bit versions of GT.M, the object code is in shared libraries, rather than individual files in the directory.

- \* The utf8 subdirectory has files called mumps, mupip, dse, lke, and so on, which are relative symbolic links to the executables in the parent directory (for example, mumps is the symbolic link ../mumps).
- \* When a shell process sources the file gtmprofile, the behavior is as follows:
  - \* If \$gtm\_chset is "m", "M" or undefined, there is no change from the previous GT.M versions to the value of the environment variable \$gtmroutines.
  - \* If \$gtm\_chset is "UTF-8" (the check is case-insensitive),
    - \* \$gtm\_dist is set to the utf8 subdirectory (that is, if GT.M is installed in /usr/lib/fis-gtm/gtm\_V6.3-010\_i686, then gtmprofile sets \$gtm\_dist to /usr/lib/fis-gtm/gtm\_V6.3-010\_i686/utf8).
    - \* On platforms where the object files have not been placed in a libgtmutil.so shared library, the last element of \$gtmroutines is \$gtm\_dist(\$gtm\_dist/..) so that the source files in the parent directory for utility programs are matched with object files in the utf8 subdirectory. On platforms where the object files are in libgtmutil.so, that shared library is the one with the object files compiled in the mode for the process.

For more information on gtmprofile, refer to the Basic Operations chapter of GT.M Administration and Operations Guide.

Although GT.M uses ICU for UTF-8 operation, ICU is not FIS software and FIS does not support ICU.

---

## Setting the environment variable TERM

The environment variable TERM must specify a terminfo entry that accurately matches the terminal (or terminal emulator) settings. Refer to the terminfo man pages for more information on the terminal settings of the platform where GT.M needs to run.

- \* Some terminfo entries may seem to work properly but fail to recognize function key sequences or fail to position the cursor properly in response to escape sequences from GT.M. GT.M itself does not have any knowledge of specific terminal control characteristics. Therefore, it is important to specify the right terminfo entry to let GT.M communicate correctly with the terminal. You may need to add new terminfo entries depending on your specific platform and implementation. The terminal (emulator) vendor may also be able to help.
- \* GT.M uses the following terminfo capabilities. The full variable name is followed by the capname in parenthesis:

```
auto_right_margin(am), clr_eos(ed), clr_eol(el), columns(cols), cursor_address(cup), cursor_down(cud1),
cursor_left(cub1), cursor_right(cuf1), cursor_up(cuu1), eat_newline_glitch(xen1), key_backspace(kbs),
key_dc(kdch1), key_down(kcud1), key_left(kcub1), key_right(kcuf1), key_up(kcuu1), key_insert(kich1),
keypad_local(rmkx), keypad_xmit(smkn), lines(lines).
```

GT.M sends keypad\_xmit before terminal reads for direct mode and READs (other than READ \*) if EDITING is enabled. GT.M sends keypad\_local after these terminal reads.

---

## Installing Compression Libraries

If you plan to use the optional compression facility for replication, you must provide the compression library. The GT.M interface for compression libraries accepts the zlib compression libraries without any need for adaptation. These libraries are included in many UNIX distributions and are downloadable from the zlib home page. If you prefer to use other compression libraries, you need to configure or adapt them to provide the same API as that provided by zlib.

If a package for zlib is available with your operating system, FIS suggests that you use it rather than building your own.

By default, GT.M searches for the libz.so shared library in the standard system library directories (for example, /usr/lib, /usr/local/lib, /usr/local/lib64). If the shared library is installed in a non-standard location, before starting replication, you must ensure that the environment variable LIBPATH (AIX) or LD\_LIBRARY\_PATH (GNU/Linux) includes the directory containing the library. The Source and Receiver Server

#### V6.3-010

link the shared library at runtime. If this fails for any reason (such as file not found, or insufficient authorization), the replication logic logs a DLLNOOPEN error and continues with no compression.

Although GT.M uses a library such as zlib for compression, such libraries are not FIS software and FIS does not support any compression libraries.

# Change History

## V6.3-010

Fixes and enhancements specific to V6.3-010:

Id	Prior Id	Category	Summary
GTM-1044	S9712-000628	Language	🔴 Next and Previous character values from \$ZATRANSFORM() 🟢
GTM-5333	C9E03-002532	Admin	See GTM-5626
GTM-5626	S9F01-002521	Admin	🔴 Replication retries indefinitely looking for a connection. 🟢
GTM-7113	-	Admin	MUPIP ROLLBACK -FETCHRESYNC tries to reconnect in case of a lost connection
GTM-8322	-	Admin	🔴 MUPIP SIZE accepts -SUBSCRIPT=<subscript> and other clean up of SIZE and INTEG 🟢
GTM-8747	-	Admin	MUPIP JOURNAL -EXTRACT -CORRUPTDB for journal extract without using the database file header(s) 🟢
GTM-8848	-	Admin	Error "nature" classification added to many MUPIP INTEG reports 🟢
GTM-8995	-	Admin	gtminstall script takes distribution tarball name ; gtmprofile script explicitly gives +rw permissions to all 🟢
GTM-9076	-	Admin	Better error messaging for file paths that exceed the maximum supported
GTM-9166	-	Admin	JNLPROCSTUCK does not produce a JNLFLUSH message
GTM-9178	-	Language	Fix for faulty ZTIMEOUT vector code trying to execute in Direct Mode
GTM-9180	-	Admin	🔴 Slight change in DSE output for bit maps
GTM-9181	-	Language	Fix for Boolean literals prior to, or within, \$SELECT()
GTM-9183	-	Language	Fix indirect exclusive NEW after a FOR
GTM-9185	-	Language	🔴 Align ZLINK behavior with MUMPS and ZCOMPILE commands
GTM-9188	-	Other	Ignore spaces between the qualifier introducer (-) and the qualifier keyword for a MUMPS command

### Change History

Id	Prior Id	Category	Summary
GTM-9190	-	Other	GT.M object files conform to current ELF standards
GTM-9193	-	Admin	Eliminate spurious message from MUPIP RECOVER
GTM-9206	-	Admin	Eliminate inappropriate MUPIP LOAD limit at 2**32 records

---

## Language

- \* ZATRANSFORM recognizes 2 (two) and -2 (minus two) as optional third arguments. 2 specifies the return of the character which collates immediately after the first character of the first argument, or the empty string if no character does. -2 specifies the return of the character which collates immediately before the first character of the first argument, or the empty string if no character does. These specifiers work in M mode for the 'M' collation (collation 0), or any user defined collation which supplies the necessary plugin functionality. In UTF-8 mode, these argument values produce a ZATRANSCOL error. If the plugin for the specified collation does not support this "next character" functionality, the function produces a COLLATIONUNDEF error in response to an attempt to invoke it. The previously supported specifiers 0 & 1 continue to work as documented. This change should not affect existing code unless it relies on the undocumented behavior that any non-zero value, and in specific 2 or -2, given as optional argument three invoked the reverse subscript collation operation. 1 is the value documented to do so. If an external collation library is used and encounters a gtm\_ac\_xutil failure, ZATRANSFORM produces an ERR\_ZATRANSCOL. If an external collation library is used and does not supply a gtm\_ac\_xutil function, ZATRANSFORM produces an ERR\_COLLATIONUNDEF when operations -2 or 2 are specified. To use these operations with external collation libraries, the libraries must supply a function called 'gtm\_ac\_xutil' with the following signature and characteristics:

```
long gtm_ac_xutil (gtm32_descriptor *in, int level, gtm32_descriptor *out, int *outlen, int op, int honor_numeric)
```

The parameter in - Supplies the input string, the first character of which is considered

The parameter level - Currently unused and should not be examined or changed

The parameter out - Supplies the one (1) character result string produced by applying the collation operation if a result was possible

The parameter outlen - Supplies to the caller the length of the returned string, which will be 0 or 1.

The parameter op - Specifies the collation operation returned:

0 - collation value of the given character

1 - character collating before the given character if it exists

2 - character collating after the given character if it exists

The parameter honor\_numeric - Boolean specifying:

TRUE - standard GT.M collation of digits before any other character

FALSE - digits should be treated the same as all other characters

The gtm\_ac\_xutil function returns 0 on success and -1 on failure.

(GTM-1044)  

- \* GT.M issues ERRWZTIMEOUT, along with the accompanying error description, in case of a run-time error in the ztimeout vector at the direct prompt. Previously, it issued GTMASSERT2 and created a core file. (GTM-9178)
- \* The GT.M compiler appropriately optimizes cases with one or more literal Boolean values prior to, or within, a \$SELECT() function. The workaround was to resolve literal expressions when producing code, which could be a challenge if they are produced by a code generator. In releases starting with V6.3-001 these cases, most typically involving nested \$SELECT() functions, could generate incorrect results or produce a GTMASSERT. (GTM-9181)
- \* GT.M supports indirect arguments that specify an exclusive operation to a NEW command on a line following a FOR command; previously such arguments produced an unsatisfactory result - typically a segmentation violation (SIG-11), but possibly some other GT.M error. (GTM-9183)
- \* ZLINK and auto-ZLINK consistently observe \$ZCOMPILE qualifiers except when they are overridden by explicit ZLINK command qualifiers, and they consequently always report an error when the routine name is invalid. Previously they observed some \$ZCOMPILE factors some of the time, and under some circumstances they eventually reported the routine could not be found. Also, explicit ZLINK observes \$ZROUTINES conventions except when the command argument or \$ZCOMPILE specifies otherwise; previously it placed the object in the current working directory. In addition, some messages associated with ZLINKFILE error contain additional context. (GTM-9185) 

---

# System Administration

- \* See GTM-5626 (GTM-5333)
- \* GT.M replication indefinitely tries to reconnect after a communication error and issues syslog messages about any errors in its attempts. Therefore, if you want to stop the retries you must explicitly stop replication. Previously, the replication servers exited without sending information about the connection issue to syslog. GT.M prints additional connection information in case of communication errors, for easier debugging. (GTM-5626) 🟡🟢
- \* MUPIP ROLLBACK -FETCHRESYNC tries to reconnect in case of a lost connection. Previously, under this condition, the rollback exited with a REPLCOMM error. (GTM-7113)
- \* MUPIP SIZE recognizes the -SU[BSCRIPT]=<subscript> qualifier to specify a global or a range of keys to estimate. The global key may be enclosed in quotation marks (" "). Identify a range by separating two subscripts with a colon (:). The -SE[LECT]=<global-name-list> and -SU[BSCRIPT]=<subscript> qualifiers are incompatible. Scan heuristic for MUPIP SIZE shows information of all levels down to the target level. Previously, it showed details only for the target level. For all heuristics, the adjacency shown is of current level. Previously, the adjacency shown was for the next lower level. In addition, MUPIP INTEG correctly handles the case of NULL subscripts, when no end key is specified; previously, it failed with a segmentation violation (SIG-11). (GTM-8322) 🟡🟢
- \* The new -CORRUPTDB qualifier for MUPIP JOURNAL -EXTRACT extracts journal records into a single file even if the database is corrupt or missing. Always specify a journal file name when you are using -CORRUPTDB. -CORRUPTDB does not recognize the wildcard character "\*" for journal file name and is incompatible with -FENCES, -LOST, and -BROKEN qualifiers. (GTM-8747) 🟢
- \* Many MUPIP INTEG error reports include a "nature" that gives some guidance on the urgency of the error corresponding to documentation in the Maintaining Database Integrity chapter of the Administration and Operations Guide. FIS recommends addressing even "Benign" errors. Previously, INTEG did not report this information. (GTM-8848) 🟢
- \* The gtminstall script recognizes the --filename command line option to specify the file name of GT.M distribution tarball and the --buildtype command line option to specify a non-production build type. Previously the file name always implicitly matched the GT.M distribution standard name and production type. The gtminstall script creates temporary working directory of the form /tmp/gtminstall\_<timestamp> and cleans up the extracted contents of distribution tarball at the end of successful installation. Previously, the temporary working directory was the directory created by mktemp on Linux and /tmp/root\_\$\$\_<timestamp> on AIX and the extracted contents were left behind after successful installation of GT.M. The gtmprofile script explicitly creates /tmp/fis-gtm if it does not exist and provides world read-write permissions. Previously the permissions of /tmp/fis-gtm depended on umask settings and might not have provided read-write permissions for all users. (GTM-8995) 🟢
- \* GT.M produces a FILEPATHTOOLONG error when it is unable to create a new (or temporary) file because of the file name (including the path) exceeding 255 chars. FILEPATHTOOLONG replaces PARBUFSM where ever it was issued but uses the same message ID. Also, the text for FNTRANSERROR now reads: Filename including path exceeded 255 chars while trying to resolve filename ffff, where ffff is the file name. Previously, GT.M did not issue PARBUFSM errors when file/path exceeded 255 characters while creating journal files or global directories. (GTM-9076)
- \* JNLPROCSTUCK warnings go to the syslog to indicate that journal file writes are taking longer than anticipated. These warnings do not represent a GT.M issue nor a failure per se. Previously, they were accompanied by a JNLFLUSH message, which, because GT.M uses it to report other conditions, customers may wish to retain as a custom error indication for starting an Instance Freeze. (GTM-9166)
- \* In order to support a change in an upcoming release (V7.0-000), DSE internally handles block numbers as 64-bit entities, however, for safety, it gives an error if it encounters a block number larger than currently supported by V6.3. Previously the field for the block number when displaying a bitmap, was not as wide. (GTM-9180) 🟡
- \* GT.M issues appropriate error messages during an interrupted MUPIP RECOVER. Previously, in rare instances, GT.M could issue an error indicating it could not delete a file that had already been deleted. This issue was only observed in the GT.M development environment, and was never reported by a user. (GTM-9193)

## System Administration

- \* MUPIP LOAD can handle a maximum of  $2^{64}$  records including the header records. BIN format has one header record and GO and ZWR formats have two. GO format uses two records per node and ZWR uses one, but BIN format typically carries many nodes per record. Previously, MUPIP LOAD terminated without error when it reached a record count of 4294967293 even when the LOAD was incomplete because there were more records in the extract. The workaround was to limit the extract to less than  $2^{32}$  records (including the header) by selecting globals and/or using temporary global directories, and/or modifying the extracts, say with an M program. (GTM-9206)

---

## Other

- \* A MUMPS command invocation ignores extra spaces between MUMPS the dash and the qualifier name for -RUN or -DIRECT when determining the value of \$ZCMDLINE. Note, as before, if you use both -direct and -run on the same command, GT.M always attempts to enter Direct Mode, and \$ZCMDLINE may have interesting contents. Previously spaces in between the dash (-) and the keyword caused the qualifier name to appear in \$ZCMDLINE. (GTM-9188)
- \* GT.M produces object files consistent with ELF standards. Previously, ELF tools such as the linker could emit warnings or errors when operating on GT.M-produced object files. [Linux x86\_64] (GTM-9190)

---

## Error and Other Messages

---

### DSEINVALBLKID

**DSEINVALBLKID**, Trying to edit DB with 64-bit block IDs using pre-V7 DSE

DSE Error: Indicates a mismatch between the version of DSE and the version of the target database

Action: Use the version of DSE that matches the database.

---

### FNTRANSERROR

**FNTRANSERROR**, Filename including path exceeded 255 chars while trying to resolve filename FFFF

All GT.M Components Error: While creating a database, resolving environment variables in a database path exceeded the maximum supported file name size.

Action: Reduce the path size by altering base components of the path or database name and/or the values of the environment variables to create a shorter overall filename and retry.

---

### PARBUFSM

Last used version: V6.3-010

**PARBUFSM**, Parse buffer too small

Run Time Error: This indicates that an attempt to parse a file-specification exceeded the maximum length for file-specifications.

Action: Review the file-specification for valid syntax; if it is a logical name / environment variable, confirm its definition.

---

### VERMISMATCH

**VERMISMATCH**, Attempt to access xxxx with version yyyy, while already using zzzz

Run Time Error: The database file xxxx is currently marked as in use by version (\$ZVERSION) zzzz, but the process attempted to access the database file with version yyyy. GT.M prevents this as different versions typically have some incompatibility in their use of the database file. This error may also occur when you make a copy of the database without performing a RUNDOWN and attempt to access it with a newer GT.M version.

Action: If you encounter this error while upgrading a database file, perform the appropriate MUPIP action using the prior GT.M version to ensure that there are no processes/semaphores attached to the database file.

---

### ZATRANSCOL

**ZATRANSCOL**, The collation requested has no implementation for the requested operation

Run Time Error: The \$ZATTRANSFORM() function requested a next or previous collation character, but the collation transform module involved does not implement that functionality.

Action: Enhance the collation transform plug-in in question to support the desired functionality

---